

Octave

GNU Octave, version 3.0.1
 Copyright (C) 2008 John W. Eaton and others.
 This is free software; see the source code for copying conditions.
 There is ABSOLUTELY NO WARRANTY; not even for MERCHANTABILITY or
 FITNESS FOR A PARTICULAR PURPOSE. For details, type 'warranty'.
 Octave was configured for "i686-pc-msdosmsvc".
 Additional information about Octave is available at <http://www.octave.org>.
 Please contribute if you find this software useful.
 For more information, visit <http://www.octave.org/help-wanted.html>
 Report bugs to <bug@octave.org> (but first, please read
<http://www.octave.org/bugs.html> to learn how to write a helpful report).
 For information about changes from previous versions, type 'news'.

- Use 'pkg list' to see a list of installed packages.
- Scite editor installed. Use 'edit' to start the editor.
- MSVS shell available (<C:\Program Files\Octave\msys>).
- Graphics backend: jhandles.

```
octave-3.0.1.exe:1 cd
octave-3.0.1.exe:2 cd Desktop/Chapter2/Octave
octave-3.0.1.exe:3 edit
octave-3.0.1.exe:4 EPSP
octave-3.0.1.exe:5
```

EPSP.m - Scite

File Edit Search View Tools Options Language Buffers Help

%% Synaptic conductance model to simulate an EPSP
 clear; clf; hold on;

%% Setting some constants and initial values
 c_m=1; g_L=1; tau_syn=1; E_syn=10; delta_t=0.01;
 g_syn(1)=0; I_syn(1)=0; v_m(1)=0; t(1)=0;

%% Numerical integration using Euler scheme
 for i=2:10/delta_t
 t(i)=t(i-1)+delta_t;
 if abs(t(i)-l)<0.001; g_syn(i)=l; end
 g_syn(i)=g_syn(i-1) - delta_t/tau_syn * g_syn(i-1);
 I_syn(i)= g_syn(i) * (v_m(i-1)-E_syn);
 v_m(i) = v_m(i-1) - delta_t/c_m * g_L* v_m(i-1) ...
 - delta_t/c_m * I_syn(i);
 end

%% Plotting results
 plot(t,v_m); plot(t,g_syn*5,'r--'); plot(t,I_syn/5,'k:')

i=1 co=1 INS (CR+LF)

